




BROOME STREET PATTERNS



# Wicked Eve

Quilt designed by Osie Lebowitz



Finished quilt: 70 $\frac{1}{2}$ " x 89"



## Fabric Requirements

One fat quarter each:

Wicked-C3763 Cloud  
Wicked-C3759 Charcoal  
Wicked-C3765 White  
Wicked-C3764 Black

1/3 yard Wicked-C3762 Black  
1/3 yard Wicked-C3758 Black  
3/4 yard Wicked-C3760 Black  
1 1/8 yards Wicked-C3761 Grey  
2 2/3 yards Wicked-C3756 Grey  
1/2 yard Tonga-B7900 Chrome  
5/8 yard Tonga-B7900 Thunder  
1 1/2 yards Tonga-B7900 Black (includes binding)  
5 1/2 yards Wicked-C3758 Black (backing)  
78" x 97" batting

## Cutting

*From Wicked-C3763 Cloud, Wicked-C3759 Charcoal, Wicked-C3765 White and Wicked-C3764 Black:*

- Cut one 10 1/2" square for Block A from each fabric.

*From both Wicked-C3762 Black and Wicked-C3758 Black:*

- Cut one 10 1/2" x 32 1/2" strip for Block B.

*From Wicked-C3760 Black:*

- Cut two 24 1/2" x 10 1/2" length-of-fabric (LOF) strips for Block C.

*From Wicked-C3761 Grey:*

- Cut one 37" x 18" LOF strip for Block D.

*From Wicked-C3756 Grey:*

- Cut four 9 1/2" x LOF strips, cutting carefully to create two darker and two lighter strips.

*From Tonga-B7900 Chrome:*

- Cut one 3 1/2" x width-of-fabric (WOF) strip. Sub-cut one 3 1/2" x 37" strip for Block D.
- Cut three 2 1/2" x WOF strips. Sub-cut two 2 1/2" x 24 1/2" strips and six 2 1/2" x 10 1/2" strips.
- Cut one 3 7/8" square and four 2 7/8" squares.

*From Tonga-B7900 Thunder:*

- Cut one 3 1/2" x WOF strip. Sub-cut one 3 1/2" x 18" strip for Block D.
- Cut five 2 1/2" x WOF strips. Sub-cut two 2 1/2" x 32 1/2" strips and six 2 1/2" x 10 1/2" strips.
- Cut one 3 7/8" square and four 2 7/8" squares.

*From Tonga-B7900 Black:*

- Cut seven 2" x WOF strips. Sub-cut four 2" x 12 1/2" strips and two 2" x 40" sashing strips. Sew the remaining WOF strips end to end using diagonal seams and cut two 2" x 48" sashing strips.
- Cut fourteen 2 1/2" x WOF strips for border 1 and binding.

## Block Construction

1. Draw a diagonal line on the wrong side of each 2 7/8" B7900 Chrome square. Place one marked square right sides together with a 2 7/8" B7900 Thunder square. Sew 1/4" on each side of the marked line. Cut the square apart on the marked line to make two half-square triangles (HST). The HST should measure

2 1/2" square. Repeat to make a total of eight HST.

2. Repeat step 1 using the 3 7/8" B7900 Chrome and 3 7/8" B7900 Thunder squares. The HST should measure 3 1/2" square.

### Block A

3. Referring to figure 1, sew a 2 1/2" x 10 1/2" C7900 Chrome rectangle to the left side of each C3763 Cloud, C3759 Charcoal, C3765 White and C3764 Black square.




fig. 1-Block A

4. Sew a 2 1/2" Chrome/Thunder HST to the left end of a 2 1/2" x 10 1/2" B7900 Thunder strip. Repeat to make a total of four pieced strips.

5. Sew one pieced strip from step 4 to the bottom of each pieced unit from step 3.

### Block B

6. Sew a 2 1/2" x 10 1/2" B7900 Chrome strip to the left side of each 10 1/2" x 32 1/2" C3762 Black and C3758 Black strip.



7. Sew a 2 1/2" HST to the left end of each 2 1/2" x 32 1/2" B7900 Thunder strip.

8. Sew the pieced strip from step 7 to the bottom of each unit from step 6. (figure 2)



fig. 2-Block B

### Block C

9. Sew a 2 1/2" x 24 1/2" B7900 Chrome strip to the left side of both 10 1/2" x 24 1/2" C3760 Black strips.

10. Sew a 2 1/2" HST to the left end of each 2 1/2" x 10 1/2" B7900 Thunder strip.

11. Sew the pieced strip from step 10 to the bottom of each unit from step 9. (figure 3)




fig. 3-Block C

### Block D

12. Sew a 3 1/2" x 37" B7900 Chrome strip to the left side of the 37" x 18" C3761 Grey strip.

13. Sew a 3 1/2" Chrome/Thunder HST to the left end of the 3 1/2" x 18" B7900 Thunder strip.

14. Sew the pieced rectangle strip from step 13 to the bottom of the unit




fig. 4-Block D

from step 12. (figure 4)

## Quilt Top Assembly

15. Following the Quilt Assembly Diagram, sew a 2" x 12½" B7900 Black sashing strip between each Block A and B, and the side A and C blocks.

16. Sew 2" x 40" B7900 Black sashing strips to both long sides of Block D.

17. Sew an A/C block unit from step 15 to each long side of the pieced unit from step 16.

18. Sew one 2" x 48" B7900 Black sashing strip to the top and the other to the bottom of the step 17 unit.

19. Sew one A/B unit from step 15 to the top and the other to the bottom of the step 18 unit.

20. For the inner border, sew six 2½" B7900 Black strips together end to end using diagonal seams. Measure the quilt length through the center of the quilt and cut two pieces that length from the pieced strip. Sew one to each side of the quilt and press.

21. Measure the quilt width through the center of the quilt and cut two pieces that length from the pieced 2½" B7900 Black strip. Sew one to the top and the other to the bottom of the quilt.

22. Mark the centers of the 9½" x LOF C3756 Grey border strips and the centers of each quilt side. Match the border centers to the center marks on the quilt, noting the print orientation and location. Referring to the quilt photo, note that the darker borders are placed on the left and bottom and the lighter borders are on the right and top of the quilt. Sew on all four borders strips starting and stopping stitching ¼" from the edge. *Do not cut off the extra fabric length.*

23. To miter the borders, fold one corner of the quilt on a 45° angle so that the border strips are directly on top of one another and the seams nest together. Place your rotary ruler on the fold of the quilt so that the long edge is against the fold and the 45° line is on the side seam. Draw a line from the corner of the quilt top to the outside edge of the border. Pin the borders together. Position your needle on the inside corner where the border meets the quilt. Stitch directly on the line you have drawn to the outside edge of the border.


Trim the excess fabric leaving a ¼" seam allowance. Press. Repeat the process for the remaining three corners of the quilt. (figure 5)

## Finishing

24. Layer the quilt top, batting and backing and quilt as desired.

25. Stitch the binding strips together end to end using diagonal seams. Fold and press the resulting long strip in half lengthwise with wrong sides together. Stitch to the quilt front, matching raw edges and mitering the corners.

26. Fold the binding to the quilt underside and hand-stitch the folded edge to the quilt back.




©2015 Osie Lebowitz

[www.fromneedleandthread.com](http://www.fromneedleandthread.com)

Permission is granted to shop owners and teachers to make copies for promotional or educational purposes only.

This pattern may not be reproduced for commercial purposes (i.e. may not be sold).

This pattern may not be reproduced for ANY PURPOSE after July 15, 2016.



Quilt Assembly Diagram